

SOP bilong 'Temperature Screening'

As tingting bilong 'screening'

As tingting bilong 'temperature screening' em long luksave long ol manmeri husat i gat ol 'symptom' bilong COVID-19.

'Temperature screening' i ken kamap long olgeta hap we planti manmeri i save go long en, ol hap we COVID-19 i ken spred. Kain ol hap olsem:

- Hotels
- Restaurants/bars/cafes/shops
- Hospitals
- Shopping centres/malls
- Stadiums
- Theatres
- Airports

Dispela em ol masin bilong mekim 'temperature screening' wok:

- 'Contactless devices' (em ol kain masin olsem. 'thermal scanners' or 'handheld infrared skin thermometers'): dispela ol masin i ken ditektim 'body temperature' taim ol i no pas long skin bilong man o meri
- 'Contact thermometers' (em ol kain masin olsem. 'tympanic', 'oral', 'axillary'): dispela kain ol masin bilong bilong mekim 'screening' bikos ol i ken trensmitim COVID-19 i go long narapela man o meri.

Rot bilong redi long mekim 'screening'

1. Makim wanpela 'screening station'

- Wanpela eria i mas stap long olgeta 'entrance points'. Sapos i gat moa long wanpela 'entrance', orait mekim olgeta manmeri i wokabout stret i go insait long wanpela 'entrance point' na i go autsait long wanpela 'exit point' na i no ken tanim i kam bek.
- Olgeta manmeri we i go insait long 'entrance' i mas sekim 'temperature' bilong ol, maski ol i kastoma, wokmanmeri, o visita.
- Dispela 'screening station' i mas i gat ol 'hand sanitiser' o wanpela 'hand washing station' na ol woklain i mas tokim ol manmeri long klinim han bilong ol taim ol i kam insait
- Ol woklain i mas lukim olsem ol manmeri i sanap long lain long kam insait long mas bihainim 'social distancing'

2. 'Screening'

- Em i gutpela long mekim 'temperature screening' wantaim ol 'handheld device' long planti hap, kain olsem, hap bilong go insait long wanpela kaibar o 'restaurant' o stua.
- Long ol ples we i gat planti manmeri i muv long wanpela taim, em i gutpela moa long yusim ol 'thermal scanners'.
- 'Symptom screening' i ken kamap long ol hap we ol manmeri bai i stap longpela taim, kain olsem ol hotel. 'Screening' i mas bihainim 'current case definition'.

- **3. Ol wokmanmeri bilong mekim 'screening'**
- I gat nid long wanpela man o meri husat bai i mekim wok bilong 'screening' tasol. Dispela man o meri i no gat nid long i gat save long sait bilong helt, tasol em i mas i gat gutpela training long ol pasin bilong 'infection prevention and control (IPC).
- Dispela man o meri i mas kisim training tu long ol polisi we i tambuim ol manmeri long kam insait sapos ol i no mekim 'screening; o sapos 'temperature' bilong ol i abrusim ol nomol mak.

4. Wokim ol tok save sain

- Redim wanpela sain na putim ples klia bai ol manmeri i ken save olsem 'screening' i wok long kamap i stap. Dispela em i impoten sapos i gat longpela lain manmeri i wok long wet i stap.

5. Rot bilong skelim ol risalt bilong 'temperature scan'

- Nomol 'body temperature' i save stap namel long '36 degree Celsius' na aninit long '37.5 degree Celsius.
- Sapos 'temperature' em i stap aninit long '36 degree Celsius', orait dispel i soim olsem masin bilong skeim 'temperature' i no wok gut. Kisim 'temperature' gen na lukim olsem yu kisim wanpela gutpela 'reading' bipo long yu larim man o meri kam insait.
- Sapos 'temperature reading' em i '37.5 degree Celcius' na i go antap, orait dispela man o meri i gat skin i hot. Sapos dispela i kamap, orait bihainim instraksen i stap long Step namba 5 daunbilu.

Rot bilong mekim 'screening'

Lukim 'flowchart'.

1.OI 'IPC measures'

Dispela man o meri husat i mekim 'screening' i mas:

- Werim wanpela 'surgical mask'
- Stap longwe long mak bilong 1.5 mita long ol narapela manmeri
- Yusim 'hand sanitiser' planti taim

2. Kisim Tok Orait bilong ol manmeri

- Bipo long kisim 'temperature reading', 'screener' i mas tok save long ol olsem em bai i kisim 'temperature reading' bilong ol
- Sapos wanpela man o meri i no laik long ol i kisim 'temperture reading' bilong em, orait ol i no ken larim em i kam insait.

3. Rot bilong sekim 'temperature'

- Long ol 'handheld scanners', **bihain instraksen i stap long 'device' bilong yu.**

- Sapos yu i no klia long wanem hap bilong bodi long mekim 'scan', mipela i rekomendim 'temporal area' (sait bilong poret), na i no nek, 'wrist' o namel bilong poret.
- Askim dispela man o meri long rausim samting we i karamapim poret bilong em. Sapos em i wanpela 'head dress' bilong lotu orait em i ken lusim i stap.
- Taim yu kisim 'temperature reading' pinis, kolim 'temperature reading' bilong dispela man o meri i go long em, bai em i ken harim.

4. Ol samting bilong bihainim sapos wokmanmeri i painim olsem wanpela i gat skinhot

- Sapos 'temperature' em i antap long '37.5 degrees Celsius', orait dispel man o meri i no ken kam insait.
- Planti kainkain samting i ken mekim na skin bilong man o meri i hot (kain olsem man o meri i stap longpela taim long san, dringim bia o 'alcohol', karamapim het bilong em wantaim sampela samting, meri gat bel, meri i lukim sik mun, 'hormone replacement therapy', mekim hatpela ekseais), askim dispela man o meri long wet liklik long ples we i kol na sekim 'temperature' bilong em gen. Eksampel, askim man o meri long rausim samting we em, i karamapim het bilong em long en, na sapos ol i tok orait weit liklik na sekim gen 'temperature' bilong em.
- Sapos 'temperature' bilong dispela man o meri i stap yet antap long 37.5 degree Celsius', orait no ken larim dispela man o meri i kam insait.
- Tok save long ol olsem ol i gat skin i hat na kolim 'temperature' bilong ol bai ol i ken save.
- Tok save long ol long go na lukim wanpela helt kea profesenol o go long wanpela haus sik we i stap klostu long mekim wanpela COVID-19 swab.
- Tok save long ol long mekim 'social distancing', werim wanpela pes mask na kus i go insait long elbo bilong ol.

Dispela tok save em i bilong ol 'hotel guests' tasol

- Larim ol 'guests' i kam insait long banis blong dispela hotel
- Tokim ol olsem ol i gat skin i hot na kolim 'temperature' reading'
- Tokim dispela man o meri long 'self isolate' insait long rum bilong hotel hariap
- Tokim dispela man o meri long bihainim 'social distancing', werim wanpela mask na kus i go insait long elbo bilong em.
- Mekim arenjmen long wanpela helt profesenol long kam na sekim gut dispela man o meri


'Temperature Screening Guideline' bilong ol 'airport', stua na hotel

Redim Envairomen

- Makim wanpela spes we i stap longwe long san i lait na hot bilong ol masin
- Putim 'thermometer' long testin erai 10-30 minit bipo long yu yusim em na larim em long adjas.

Instraksen bilong 'screener'

- Werim wanpela medikol mask long olgeta taim
- Stap longwe long mak bilong 1.5 mita
- Yusim 'hand sanitizer' olgeta taim



*Long olgeta masin, bihainim instraksen bilong manufektura bilong dispela masin.

- Tokaut klia long dispela man o meri olsem yupela bai kisim 'temperature' bilong ol
- **Posisen:** Putim 'thermometer' long poret ('right temple')
- **Distens:** Bihainim instraksen bilong manufektura, holim masin 2-5 cm long poret
- NO ken tasim 'senor' bilong masin

'Temperature' i antap long 37.5C

Sekim 'temeperature' gen bihain long 5-pela minit

'Temperature' i antap long 37.5C

Givim tok save: 'sneeze'/kus i go insait long elbo, werim wanpela mask, mekim 'physical

'Temperature' i aninit long

Larim man o meri i go insait

Long ol hotel:

Larim ol manmeri i kam insait

Tokim ol long 'self-isolate insait long wanpela rum bilong hotel.

Long ol stua/'mall'

No ken larim ol manmeri i kam insait, tokim ol long lukim wanpela helt kea profesenol

Long ol 'airport'

Tok save long ol 'airport health